

SOFTWARE UPGRADE PROCEDURE FOR CAMBRIDGE 1.0

1. Download the Software file “CH05100572-B63_DSD2104iMH IRDETO SIGNED APPLICATION SOFTWARE IMAGE (V1.67)” from the website.


Cambridge 1.0

1.67

June 2015

 Software Update


2. Extract the zip file and save the “Irdeto_238_07.SDL” file to the USB.



3. Ensure that “Irdeto_238_07.SDL” is placed in the root folder of your USB storage device.



4. Insert the USB device into the side or rear USB slot.
5. Using your My-HD Cambridge 1.0 remote control, Press the **MENU** button, then Go to **SETTINGS**.



6. Select **SOFTWARE UPDATE**, then Key in the pin code 0000 when prompted.




7. Select **USB UPGRADE** from the option.




8. Select **OK** to confirm.



9. System will reboot and check for USB software upgrade software.



10. Software upgrade on process. DO NOT TURN OFF/SWITCH OFF THE DEVICE WHILE UPGRADE IS ON PROCESS.



11. Once software upgrade is complete, My-HD Cambridge 1.0 receiver will reboot, and will go to the screen below.

