

SOFTWARE UPGRADE PROCEDURE FOR HUMAX IR3100HD / MYHD


IMPORTANT : Please note that after the software upgrade process, your Humax IR 3100HD will reset into its factory default settings. All personal settings and favorite list will be deleted.

1. Download the Software file “IR3100HD_V10108_L5.ZIP” from the website.


Humax IR-3100 HD

1.01.08

December 2014

 Software Update

2. Extract the zip file and save the two files “IR3100HD_V10108_L5.sdl ” and “upgrade.dsc” file to the USB.




3. Ensure that the two files are placed in the root folder of your USB storage device.




4. Insert the USB device into the rear USB slot.
5. Turn on the STB with a long press of the channel down button on the front panel.



6. Release the channel down button when the download starts.



7. The STB turns off and on automatically when the downloading is complete.



8. STB will boot up to the initial setup screen wizard to reconfigure the service.



